



Frequently Asked Questions

Topic: Dr. Engrave Software

ST51500

1. Will Dr. Engrave work with Windows® 95, Windows® 98, or Windows® NT 4.0?

Yes, Dr. Engrave is a 32 bit application software for Windows® 95/98/NT.

2. Can Dr. Engrave create stroke fonts to minimize engraving time?

Yes, Dr. Engrave can create stroke fonts to minimize the time for engraving. Stroke fonts created by Dr. Engrave can be modified by using the single font edit command.

3. Can Dr. Engrave import a Microsoft Excel file in CSV. format?

Yes, Dr. Engrave can import data in CSV format from other applications to produce layouts for text boxes. This allows you to engrave many different text strings (for example, many different names) with the same format (uniform text boxes) very quickly.

4. System requirement:

Windows® 95:

- Processor = I486SX is required (Pentium 100 MHz is recommended)
- System Memory = 8 MB is required (16 MB recommended)
- Hard Disk = 3.5 MB of free space

Windows® 98/NT:

- Processor = I486DX (Pentium 100 MHz recommended)
- System Memory = 16 MB is required (32 MB recommended)
- Hard Disk = 3.5 MB of free space

Disclaimer: All of the information contained in this document is based on the information available at the time of its creation. In no event will Roland DGA Corporation be liable for any damages, including damages for loss of business profits, business interruption, loss of business information and the like arising out of the use of or inability to use these materials.